



Onsight RealWear Voice Commands

Copyright

Librestream HMT Voice Commands Guide

Doc #: 400384-01 Rev: D

November 2022 (v11.4.16)

Information in this document is subject to change without notice. Reproduction in any manner whatsoever without the written permission of Librestream is strictly forbidden.

Copyright Notice:

Copyright 2004-2022 Librestream Technologies Incorporated. All Rights Reserved.

Patents Notice:

United States Patent # 7,221,386, together with additional patents pending in Canada, the United States, and other countries, all of which are in the name of Librestream Technologies Inc.

Trademark Notice

Librestream, the Librestream logo, Onsight, the Onsight logo, Onsight Connect, Onsight Flow, Onsight Workspace, Onsight Cube, Onsight Collaboration Hub, Onsight Smartcam, Onsight Platform Manager, and Onsight Tealink are either registered trademarks or trademarks of Librestream Technologies Incorporated in Canada, the United States, European Union and/or other countries. All other trademarks are the property of their respective owners.

Contents

Copyright.....	ii
1. Common Commands.....	5
2. Login Commands.....	9
3. System Health Commands.....	15
4. Contact Commands.....	17
5. Call Commands.....	19
6. File System.....	27
7. ViewFinder Commands.....	33
8. Show Information Commands.....	39
9. Cube Commands.....	41
Index.....	a

1. Common Commands

English, French, Chinese, and Spanish


 **Note:** This guide applies to Onsite Connect 11.4.6. and higher.

Table 1-1 English, French, Chinese, and Spanish Common Commands

English	French	Chinese	Spanish	Action
Show Tool Tips	Afficher les Infobulles	显示工具提示	Mostrar la información sobre herramientas	Shows the tooltips overlay
Hide Tool Tips	Cacher les Infobulles	隐藏工具提示	Ocultar información sobre herramientas	Hides the overlay showing tooltips
Show Help	Afficher l'aide	显示帮助	Mostrar Ayuda	Show the RealWear Help System.
Hide Help	Masquer l'aide	隐藏帮助	Ocultar Ayuda	Hide the RealWear Help System.
Hide	Masquer	隐藏	Ocultar	Prefixes various names to hide the associated view
Show	Afficher	显示	Mostrar	Prefixes various names to show the associated view
Select item #	Sélectionnez l'élément 1...	选择第某项 (1...)	Elemento 1...	Selects a specific item
Navigate Back	Retour En Arrière	转到上一页	Ir atrás	Returns to the previous screen.
Navigate Home	Menu Principal	回到主页	Regresar a Inicio	Returns the system to the Home screen
Scroll Up	Défiler vers le Haut	向上滚动	Subir	Scroll up in a list
Scroll Down	Défiler vers le Bas	向下滚动	Bajar	Scroll down in a list
Application Management				
Logout	Déconnexion	等出	Cerrar Sesión	Logout
Recent Applications	Applications récentes	最新的应用	Aplicaciones recientes	Shows the list of recent applications
Dismiss All	Tout rejeter	关闭全部	Descartar todo	Closes all recently opened applications
Dismiss Item #	Rejeter l'élément 1...	关闭第某项 (1...)	Descartar artículo 1...	Closes a specific application

English, German, Italian, and Japanese

Table 1-2 English, German, Italian, and Japanese Common Commands

English	German	Italian	Japanese	Action
Show Tool Tips	Tooltips anzeigen	Mostra i suggerimenti	ツールヒントを表示	Shows the tooltips overlay
Hide Tool Tips	Tooltips ausblenden	Nascondi i suggerimenti	ツールヒントを隠す	Hides the overlay showing tooltips
Show Help	Hilfe anzeigen	Mostra Aiuto	ヘルプを表示	Show the RealWear Help System.
Hide Help	Hilfe ausblenden	Nascondi Aiuto	ヘルプを隠す	Hide the RealWear Help System.

Table 1-2 English, German, Italian, and Japanese Common Commands (continued)

English	German	Italian	Japanese	Action
Hide	Ausblenden	Nascondi	隠す	Prefixes various names to hide the associated view
Show	Anzeigen	Mostra	表示	Prefixes various names to show the associated view
Select item #	Objekt 1...	Seleziona Elemento 1...	項目 1... から	Selects a specific item
Navigate Back	Schritt zurück	Torna indietro	前の画面	Returns to the previous screen.
Navigate Home	Hauptmenü	Menu Principale	ホーム画面	Returns the system to the Home screen
Scroll Up	Nach oben scrollen	Scorri in alto	スクロールアップ	Scroll up in a list
Scroll Down	Nach unten scrollen	Scorri in basso	スクロールダウン	Scroll down in a list
Application Management				
Logout	Abmelden	Disconnessione	ログアウト	Logout
Recent Applications	Aktuelle Anwendungen	Applicazioni Recenti	起動中のアプリ	Shows the list of recent applications
Dismiss All	Alle verwerfen	Chiudi tutto	すべてを消去する	Closes all recently opened applications
Dismiss Item #	Objekt 1... verwerfen	Chiudi elemento 1...	アイテム 1... を消去する	Closes a specific application

English, Korean, Portuguese (Brazil) and Russian

Table 1-3 English, Korean, Portuguese (Brazil) and Russian Common Commands

English	Korean	Portuguese (Brazil)	Russian	Action
Show Tool Tips	도구 도움말 표시	Mostrar dicas de ferramentas	Показать подсказки	Shows the tooltips overlay
Hide Tool Tips	도구 도움말 표시하지 않음	Ocultar dicas de ferramentas	Скрыть подсказки	Hides the overlay showing tooltips
Show Help	도움말 표시	Mostrar Ajuda	Показать помощь	Show the RealWear Help System.
Hide Help	도움말 숨기기	Ocultar Ajuda	Убрать помощь	Hide the RealWear Help System.
Hide	표시하지 않음	Ocultar	Скрыть	Prefixes various names to hide the associated view
Show	표시	Mostrar	Показать	Prefixes various names to show the associated view
Select item #	항목 1... 선택	Selecione Item 1...	Выбрать элемент 1...	Selects a specific item
Navigate Back	뒤로 가기	Tela Anterior	Переход назад	Returns to the previous screen.
Navigate Home	홈화면	Ir a tela inicial	Главное Меню	Returns the system to the Home screen
Scroll Up	위로 스크롤	Rolar para cima	Прокрутить вверх	Scroll up in a list
Scroll Down	아래로 스크롤	Rolar para baixo	Прокрутить вниз	Scroll down in a list
Application Management				
Logout	로그아웃	Logoff (Pending Future Release)	Выход	Logout

Table 1-3 English, Korean, Portuguese (Brazil) and Russian Common Commands (continued)

English	Korean	Portuguese (Brazil)	Russian	Action
Recent Applications	최근 응용 프로그램	Aplicações recentes	Последние приложения	Shows the list of recent applications
Dismiss All	모두 닫기	Dispensar todos	Отклонить все	Closes all recently opened applications
Dismiss Item #	항목 1... 닫기	Dispensar item 1...	Отклонить элемент 1...	Closes a specific application

2. Login Commands

English, French, Chinese, and Spanish

Table 2-1 English, French, Chinese, and Spanish Login Commands

English	French	Chinese	Spanish	Action
Best Practice for Login				
Scan Code	Lire le Code	扫描代码	Escanear el Código	Scan a QR code in order to perform a login
Standard Login Method				
User Name	Nom d'Utilisateur	用户名	Nombre de Usuario	Select the user name field for editing
Password	Mot de Passe	密码	Contraseña	Select the password field for editing
Show Password	Afficher le Mot de Passe	显示密码	Mostrar Contraseña	Toggles the view of a password input field between *'s and the actual password characters
Remember Me	Memoriser	记住帐户	Recordarme	Toggle to enable or disable auto login and auto registration of Onsite services
Login	Connexion	登录	Iniciar sesión	Register credentials to access Onsite services
Capture Mode	Mode de Capture	抓拍模式	Modo de captura	Enables Capture Mode operation of Onsite (For first time Onsite usage only)
Forgot Password	Mot de passe oublié	忘记密码	¿Olvidó su contraseña?	Brings up the browser to Reset the Password
Reset Password	Réinitialiser le mot de passe	重置密码	Restablecer contraseña	Triggers the sending of an email link to reset the Password
Cancel	Annuler	取消	Cancelar	Cancel some operation
Browser Back	Retour Navigateur	浏览器后退	Navegador Atras	Brings back the previous browser page (Reset Password page)
Register	Inscription	注册	Registrar	Brings up the browser for Onsite Self Registration
Logout	Déconnexion	退出	Cerrar Sesión	Logout
Enabling Single Sign On				
Settings	Réglages	设置	Configuraciones	Prefixed by "show" or "hide" to show/ hide the settings view
Login	Connexion	登录	Iniciar sesión	Brings up the Login Settings
Enable Single Sign On	activer l'authentification unique	启用单点登录	Habilitar inicio de sesión único	Toggle to enable or disable Single Sign On

Table 2-1 English, French, Chinese, and Spanish Login Commands (continued)

English	French	Chinese	Spanish	Action
Domain	Domaine	域	Dominio	Select the Domain name field for editing
Preferred User Agent	L'Agent Utilisateur Préféré	首选单点登陆用户代理	Agente de Usuario Preferido	Select the preferred user agent field for editing
Close	Fermer	关闭	Cerrar	Close the current view
Setting up a Proxy Server				
Proxy	Proxy	代理	Proxy	Brings up the Proxy Settings
Proxy Type	Type de Proxy	代理类型	Tipo de proxy	Select the Proxy Type field for editing
Address	Adresse	地址	Dirección	Select the Address field for editing
Port	Port	港口	Puerto	Select the Port field for editing
Bypass proxy server for local addresses	Contourner le serveur proxy pour les Adresses locales	绕过代理服务器以获取本地地址	Ignorar el servidor proxy para las direcciones locales	Toggles to enable or disable Bypassing proxy server for local addresses
Username	Nom d'utilisateur	用户名	Nombre de Usuario	Select the Username field for editing
Password	Mot de Passe	密码	Contraseña	Select the Password field for editing

English, German, Italian, and Japanese

Table 2-2 English, German, Italian, and Japanese Login Commands

English	German	Italian	Japanese	Action
Best Practice for Login				
Scan Code	Code scannen	Scansione codice	コードをスキャンする スキャンコード (11.4.11)	Scan a QR code in order to perform a login
Standard Login Method				
User Name	Benutzername	Nome utente	ユーザー名	Select the user name field for editing
Password	Passwort	Password	パスワード	Select the password field for editing
Show Password	Passwort anzeigen	Mostra password	パスワードを表示する	Toggles the view of a password input field between *'s and the actual password characters
Remember Me	Meine Angaben speichern	Ricordami	自動ログイン	Toggle to enable or disable auto login and auto registration of Onsite services
Login	Anmeldung	Accesso	ログイン	Register credentials to access Onsite services

Table 2-2 English, German, Italian, and Japanese Login Commands (continued)

English	German	Italian	Japanese	Action
Capture Mode	Aufzeichnungsmodus	Modalità di acquisizione	キャプチャモード	Enables Capture Mode operation of OnSight (For first time OnSight usage only)
Forgot Password	Passwort vergessen	Password dimenticata	パスワードを忘れた	Brings up the browser to Reset the Password
Reset Password	Passwort zurucksertzen	Reimposta password	パスワードのリセット	Triggers the sending of an email link to reset the Password
Cancel	Abbrechen	Annulla	キャンセル	Cancel some operation
Browser Back	browser zuruck	Browser Indietro	ブラウザバック	Brings back the previous browser page (Reset Password page)
Register	Registrieren	Registrati	登録する	Brings up the browser for OnSight Self Registration
Logout	Abmelden	Disconnessione	ログアウト	Logout
Enabling Single Sign On				
Settings	Einstellungen	Impostazioni	設定	Prefixed by “show” or “hide” to show/ hide the settings view
Show Settings (Japanese Specific)			設定を表示 (11.4.11)	Show the settings view (Japanese Specific)
Hide Settings (Japanese Specific)			設定を隠す (11.4.11)	Hide the settings view (Japanese Specific)
Login	Anmeldung	Accesso	ログイン	Brings up the Login Settings
Enable Single Sign On	Single Sign-On aktivieren	Abilita Single Sign On	シングルサインオンを有効にする	Toggle to enable or disable Single Sign On
Domain	Domäne	Dominio	ドメイン	Select the Domain name field for editing
Preferred User Agent	Bevorzugter Benutzeragent	Agente utente preferito	優先ユーザーエージェント	Select the preferred user agent field for editing
Close	Schliessen	Chiudi	終了	Close the current view
Setting up a Proxy Server				
Proxy	Proxy	Proxy	プロキシ	Brings up the Proxy Settings
Proxy Type	Proxy-Typ	Tipo di proxy	プロキシタイプ	Select the Proxy Type field for editing
Address	Adresse	Indirizzo	アドレス	Select the Address field for editing
Port	Port	Porta	ポート	Select the Port field for editing

Table 2-2 English, German, Italian, and Japanese Login Commands (continued)

English	German	Italian	Japanese	Action
Bypass proxy server for local addresses	Proxy-Server für lokale Adressen umgehen	Bypassa il server proxy per gli indirizzi locali	ローカルアドレスのプロキシサーバーを バイパスする	Toggles to enable or disable Bypassing proxy server for local addresses
Username	Benutzername	Nome utente	ユーザー名	Select the Username field for editing
Password	Passwort	Password	パスワード	Select the Password field for editing

English, Korean, Portuguese (Brazil) and Russian

Table 2-3 English, Korean, Portuguese (Brazil) and Russian Login Commands

English	Korean	Portuguese (Br)	Russian	Action
Best Practice for Login				
Scan Code	스캔 코드	Leitor De Codigo de Barras	Сканировать код	Scan a QR code in order to perform a login
Standard Login Method				
User Name	사용자 이름	Nome do usuário	Имя пользователя	Select the user name field for editing
Password	비밀번호	Senha	Пароль	Select the password field for editing
Show Password	비밀번호 표시	Mostrar Senha	Показать пароль	Toggles the view of a password input field between *'s and the actual password characters
Remember Me	기억하기	Lembrar-me	Запомнить меня	Toggle to enable or disable auto login and auto registration of Onsite services
Login	로그인	Logon	Вход в систему	Register credentials to access Onsite services
Capture Mode	캡처 모드	Modo Captura	Режим съемки	Enables Capture Mode operation of Onsite (For first time Onsite usage only)
Forgot Password	비밀번호종 및어 버렸습 니다	Esqueci a senha	Забыли пароль?	Brings up the browser to Reset the Password
Reset Password	비밀번호 재설정	Redefinir senha	Сбросить Пароль	Triggers the sending of an email link to reset the Password
Cancel	취소	Cancelar	Отмена	Cancel some operation
Browser Back	브라우저로돌아 가기	Navegador Voltar	браузер назад	Brings back the previous browser page (Reset Password page)
Register	등록	Registrar	Регистрация	Brings up the browser for Onsite Self Registration

Table 2-3 English, Korean, Portuguese (Brazil) and Russian Login Commands (continued)

English	Korean	Portuguese (Br)	Russian	Action
Logout	로그아웃	Logoff (Not supported in 11.4.6)	Выход	Logout
Enabling Single Sign On				
Settings	설정	Configurações	Настройки	Prefixed by “show” or “hide” to show/ hide the settings view
Login	로그인	Logon	Вход в систему	Brings up the Login Settings
Enable Single Sign On	싱글 사인 온 활성화	Habilitar o Single Sign On	Включить единый вход	Toggle to enable or disable Single Sign On
Domain	도메인	Domínio	Домен	Select the Domain name field for editing
Preferred User Agent	선호되는 사용자 에이전트	Agente do usuário preferencial	Предпочитаемый пользовательский агент	Select the preferred user agent field for editing
Close	종료	Fechar	Заккрыть	Close the current view
Setting up a Proxy Server				
Proxy	프록시	Proxy	Прокси-сервер	Brings up the Proxy Settings
Proxy Type	프록시 유형	Tipo de proxy	Тип прокси-сервера	Select the Proxy Type field for editing
Address	주소	Endereço	Адрес	Select the Address field for editing
Port	포트	Porta	Порт	Select the Port field for editing
Bypass proxy server for local addresses	로컬 주소에 대한 프록시 서버 우회	Ignorar o servidor proxy para endereços locais	Не использовать прокси-сервер для локальных адресов	Toggles to enable or disable Bypassing proxy server for local addresses
Username	사용자 이름	Nome do usuário	Имя пользователя	Select the Username field for editing
Password	비밀번호	Senha	Пароль	Select the Password field for editing

3. System Health Commands

English, French, Chinese, and Spanish

Table 3-1 English, French, Chinese, and Spanish System Health Commands

English	French	Chinese	Spanish	Action
Show System Health	Afficher Santé du Système	显示系统状况	Mostrar Estado del sistema	Shows the system health view
System Health	Santé du Système	系统状况	Estado del sistema	Prefixed by "show" or "hide" to show/hide the system health view
Hide	Masquer	隐藏	Ocultar	Prefixes various names to hide the associated view
Details	Détails	详情	Detalles	Brings up the details information page of the system

English, German, Italian, and Japanese

Table 3-2 English, German, Italian, and Japanese System Health Commands

English	German	Italian	Japanese	Action
Show System Health	Anzeigen Systemzustand	Mostra integrità del sistema	表示する システムヘルス システムヘルスを表示 (11.4.11)	Shows the system health view
System Health	Systemzustand	Integrità del sistema	システムヘルス	Prefixed by "show" or "hide" to show/hide the system health view
Hide	Ausblenden	Nascondi	隠す	Prefixes various names to hide the associated view
Hide System Health			システムヘルスを隠す (11.4.11)	Hides the system health view
Details	Details	Dettagli	詳細	Brings up the details information page of the system

English, Korean, Portuguese (Brazil) and Russian

Table 3-3 English, Korean, Portuguese (Brazil) and Russian System Health Commands

English	Korean	Portuguese (Br)	Russian	Action
Show System Health	표시 시스템 상태	Mostrar saúde do sistema	Показать Работоспособность системы	Shows the system health view
System Health	시스템 상태	Saúde do sistema	Работоспособность системы	Prefixed by "show" or "hide" to show/hide the system health view
Hide	표시하지 않음	Ocultar	Скрыть	Prefixes various names to hide the associated view
Details	상세 정보	Detalhes	Сведения	Brings up the details information page of the system

4. Contact Commands

English, French, Chinese, and Spanish

Table 4-1 English, French, Chinese, and Spanish Contact Commands

English	French	Chinese	Spanish	ACTION
Contacts	Contacts	联系人	Contactos	Prefixed by "show" or "hide" to show/hide the contacts list
Search Contacts	Rechercher les Contacts	搜索联系人	Buscar contactos	Search the contact list for the entered name
Scroll Up	Défiler vers le Haut	向上滚动	Subir	Scroll up in a list
Scroll Down	Défiler vers le Bas	向下滚动	Bajar	Scroll down in a list
Select item #	Sélectionnez l'élément 1...	选择第某项 (1...)	Elemento 1...	Say the item # to initiate a call.
Call [Name]	Appeler [Nom]	致电[姓名]	Llamar [Name]	Initiate a call to a user by name

English, German, Italian, and Japanese

Table 4-2 English, German, Italian, and Japanese Contact Commands

English	German	Italian	Japanese	ACTION
Contacts	Kontakte	Contatti	連絡先	Prefixed by "show" or "hide" to show/hide the contacts list
Show Contacts (Japanese Specific)			連絡先を表示する (11.4.11)	Show the contacts list (Japanese Specific)
Hide Contacts (Japanese Specific)			連絡先を隠す(11.4.11)	Hide the contacts list (Japanese Specific)
Search Contacts	Kontakte durchsuchen	Cerca contatti	連絡先を検索する	Search the contact list for the entered name
Scroll Up	Nach oben scrollen	Scorri in alto	スクロールアップ	Scroll up in a list
Scroll Down	Nach unten scrollen	Scorri in basso	スクロールダウン	Scroll down in a list
Select item #	Objekt 1...	Seleziona Elemento 1...	項目 1...	Say the item # to initiate a call.
Call [Name]	Anruf [Name]	Chiama [Name]	[Name] にコールする	Initiate a call to a user by name

English, Korean, Portuguese (Brazil) and Russian

Table 4-3 English, Korean, Portuguese (Brazil) and Russian Contact Commands

English	KOREAN	PORTUGUESE (Brazil)	Russian	ACTION
Contacts	연락처	Contatos	Контакты	Prefixed by "show" or "hide" to show/hide the contacts list
Search Contacts	연락처 조회	Pesquisar contatos	Поиск контактов	Search the contact list for the entered name
Scroll Up	위로 스크롤	Rolar para cima	Прокрутить вверх	Scroll up in a list

Table 4-3 English, Korean, Portuguese (Brazil) and Russian Contact Commands (continued)

English	KOREAN	PORTUGUESE (Brazil)	Russian	ACTION
Scroll Down	아래로 스크롤	Rolar para baixo	Прокрутить вниз	Scroll down in a list
Select item #	항목 1... 선택	Selecione Item 1...	Выбрать элемент 1...	Say the item # to initiate a call.
Call [Name]	[Name]에게 전화	Chamar [Name]	Позвонить [Name]	Initiate a call to a user by name

5. Call Commands

English, French, Chinese, and Spanish

Table 5-1 English, French, Chinese, and Spanish Call Commands

English	French	Chinese	Spanish	Action
Making a Call				
Call [Name]	Appeler [Nom]	致电[姓名]	Llamar [Name]	Initiate a call to a user by name
Cancel	Annuler	取消	Cancelar	Cancel some operation
Disconnect Call	Déconnecter l'Appel	中断通话	Desconectar llamada	Hang up the current call
Receiving a Call				
Accept	Accepter	接受	Aceptar	Accept the incoming call
Decline	Refuser	拒绝	Rechazar	Decline the incoming call
Active Call Commands				
Start Streaming	Commencer la Diffusion en Continu	开始流播	Iniciar la transmisión	Start streaming the current video to others in the current call
Stop Streaming	Arrêter la Diffusion en Continu	停止流播	Detener la transmisión	Stop streaming the current video to others in the current call
Take Picture	Prendre une Photo	拍摄照片	Tomar foto	Take a picture from the current video
Share Picture	Partager la Photo	共享图片	Compartir foto	Take a picture and share it with others in the current call
Share High Res	Partager La haute résolution	贡献高清晰度	Compartir AltaResolución	Share the high-resolution version of the current file with others in the current call
Stop Sharing	Arrêter le Partage	停止共享	Dejar de Compartir	Stop sharing an image with others in the current call
Start Recording	Commencer l'Enregistrement	开始录制	Iniciar la Grabación	Start recording the current video
Stop Recording	Arrêter l'Enregistrement	停止录制	Detener la Grabación	Stop recording the current video
Zoom Level 1	Niveau de Zoom 1	缩放等级1	Zoom nivel 1	Zoom the video to level 1
Zoom Level 2	Niveau de Zoom 2	缩放等级2	Zoom nivel 2	Zoom the video to level 2
Zoom Level 3	Niveau de Zoom 3	缩放等级3	Zoom nivel 3	Zoom the video to level 3
Telestration Commands				
Telestrate Arrow	Flèche de Téléstrate	远程示范箭头	Dibujar flecha	Create a telestration arrow on the current video
Telestrate Circle	Cercle de Téléstrate	远程示范圆圈	Dibujar círculo	Create a telestration circle on the current video
Telestrate Rectangle	Rectangle de Téléstrate	远程示范长方形	Dibujar rectángulo	Create a telestration rectangle on the current video

Table 5-1 English, French, Chinese, and Spanish Call Commands (continued)

English	French	Chinese	Spanish	Action
Telestration Colors	Couleurs de Téléstrate	远程示范色彩	Colores de la telestración	Show a popup letting the user select the telestration color
Hide Telestration Colors	Masquer les Couleurs de Téléstration	隐藏远程示范色彩	Ocultar los colores de la telestración	Hides the colors popup when choosing telestration colors
Erase Telestration	Effacer la Téléstration	擦除远程示范	Borrar telestración	Erase the current telestration
Undo Telestration	Annuler la Téléstration	撤销远程示范	Deshacer la Telestración	Deletes the most recent telestration
Translator Commands				
Translator	Traducteur	翻译器	Traductor	Displays the Translator settings
Hide Translator	Masquer le traducteur	隐藏翻译器	Mostrar Traductor	Hides the Translator settings
Captions	Sous-titres	字幕	Leyendas	Toggle to enable or disable captions
Translate from	Traduire de	译自	Traducir de	Brings drop down menu for Languages
To	À	至	A	Brings drop down menu for Languages
Additional Settings				
Toggle Mic (Microphone)	Basculer le Microphone	麦克风开关	Alternar el Micrófono	Turns the microphone on or off
Toggle Telephoto	Basculer le Téléobjectif	切换长焦	Alternar teleobjetivo	Turns the telephoto mode on or off (Navigator 500)
Mute Microphone	Couper le microphone	静音麦克风	Silenciar Micrófono	Mutes the Mic at the system level
Toggle Torch	Basculer la Torche	火炬开关	Alternar la Linterna	Turns the camera light on or off

English, German, Italian, and Japanese

Table 5-2 English, German, Italian, and Japanese Call Commands

English	German	Italian	Japanese	Action
Making a Call				
Call [Name]	Anruf [Name]	Chiama [Name]	コールを切断する	Initiate a call to a user by name
Cancel	Abbrechen	Annulla	キャンセル	Cancel some operation
Disconnect Call	Verbindung trennen	Termina la chiamata	コールを切断する コールを終了する (11.4.11)	Hang up the current call

Table 5-2 English, German, Italian, and Japanese Call Commands (continued)

English	German	Italian	Japanese	Action
Receiving a Call				
Accept	Annehmen	Accetta	承認 する 応答 (11.4.11)	Accept the incoming call
Decline	Ablehnen	Rifiuta	拒絶 拒否 (11.4.11)	Decline the incoming call
Active Call Commands				
Start Streaming	Streaming starten	Avvia streaming	ストリーミングを開始する	Start streaming the current video to others in the current call
Stop Streaming	Streaming beenden	Arresta streaming	ストリーミングを停止する	Stop streaming the current video to others in the current call
Take Picture	Foto aufnehmen	Scatta foto	写真 を撮る	Take a picture from the current video
Share Picture	Foto teilen	Condividi foto	写真 を共有する	Take a picture and share it with others in the current call
Share High Res	Hohe Auflösung teilen	Condividi in alta risoluzione	高解像度を共有する 高画質写真を共有 (11.4.11)	Share the high-resolution version of the current file with others in the current call
Stop Sharing	Freigabe beenden	Arresta condivisione	共有を止停止する	Stop sharing an image with others in the current call
Start Recording	Aufnahme starten	Avvia registrazione	録画を開始する	Start recording the current video
Stop Recording	Aufnahme beenden	Arresta registrazione	録画を止停 する	Stop recording the current video
Zoom Level 1	Zoomstufe 1	Ingrandisci al livello 1	ズームレベル1	Zoom the video to level 1
Zoom Level 2	Zoomstufe 2	Ingrandisci al livello 2	ズームレベル2	Zoom the video to level 2
Zoom Level 3	Zoomstufe 3	Ingrandisci al livello 3	ズームレベル3	Zoom the video to level 3
Telestration Commands				
Telestrate Arrow	Pfeil für Videomarkierung	Disegna freccia	矢印を テレストレートする アノテーション、矢印 (11.4.11)	Create a telestration arrow on the current video
Telestrate Circle	Kreis für Videomarkierung	Disegna cerchio	円形をテレストレートする アノテーション、遠景 (11.4.11)	Create a telestration circle on the current video

Table 5-2 English, German, Italian, and Japanese Call Commands (continued)

English	German	Italian	Japanese	Action
Telestrate Rectangle	Rechteck für Videomarkierung	Disegna rettangolo	四角をテレストレートする アノテーション、四角 (11.4.11)	Create a telestration rectangle on the current video
Telestration Colors	Farben für Videomarkierung	Colori note sullo schermo	テレストレーション カラー アノテーション色 (11.4.11)	Show a popup letting the user select the telestration color
Hide Telestration Colors	Videomarkierungs-Farben ausblenden	Nascondi colori delle note sullo schermo	テレストレーションカラーを隠す アノテーション色を隠す (11.4.11)	Hides the colors popup when choosing telestration colors
Erase Telestration	Videomarkierung löschen	Cancella note sullo schermo	テレストレーションを消去する アノテーションを削除 (11.4.11)	Erase the current telestration
Undo Telestration	Videomarkierung rückgängig machen	Annulla note sullo schermo	テレストレーションを元に戻す アノテーションを元に戻す (11.4.11)	Deletes the most recent telestration
Translator Commands				
Translator	übersetzer	Traduttore	翻訳者 翻訳機能 (11.4.11)	Displays the Translator settings
Hide Translator	Übersetzer verbergen	Nascondi Traduttore	トランスレーターを隠す 翻訳機能を隠す (11.4.11)	Hides the Translator settings
Captions	Bildunterschriften	Sottotitoli	キャプション	Toggle to enable or disable captions
Translate from	übersetzen von	Traduci da	翻訳元の言語	Brings drop down menu for Languages
To	nach	A	翻訳先の言語	Brings drop down menu for Languages
Additional Settings				
Toggle Mic (Microphone)	Mikrofon umschalten	Attiva/disattiva microfono	マイクを切り替える	Turns the microphone on or off
Toggle Telephoto	Tele umschalten	Abilita/disabilita il teleobiettivo	望遠に切り替える	Turns the telephoto mode on or off (Navigator 500)
Mute Microphone	Mikrofon aus	Disabilita Microfono	マイクを無効にする	Mutes the Mic at the system level

Table 5-2 English, German, Italian, and Japanese Call Commands (continued)

English	German	Italian	Japanese	Action
Toggle Torch	Lampe umschalten	Attiva/disattiva torcia	トグルトーチ トグルライト (11.4.11)	Turns the camera light on or off

English, Korean, Portuguese (Brazil) and Russian

Table 5-3 English, Korean, Portuguese (Brazil) and Russian Call Commands

English	Korean	Portuguese (Brazil)	Russian	ACTION
Making a Call				
Call [Name]	[Name]에게 전화	Chamar [Name]	Позвонить [Name]	Initiate a call to a user by name
Cancel	취소	Cancelar	Отменить	Cancel some operation
Disconnect Call	통화 끊기	Desconectar chamada	Отключить звонок	Hang up the current call
Receiving a Call				
Accept	수락	Aceitar	Принять	Accept the incoming call
Decline	거부	Recusar	Отклонить	Decline the incoming call
Active Call Commands				
Start Streaming	스트리밍 시작	Iniciar transmissão	Начать потоковую передачу	Start streaming the current video to others in the current call
Stop Streaming	스트리밍 중지	Parar transmissão	Остановить потоковую передачу	Stop streaming the current video to others in the current call
Take Picture	사진 찍기	Tirar foto	Сделать снимок	Take a picture from the current video
Share Picture	사진 공유	Compartilhar imagem	Общий доступ к снимку	Take a picture and share it with others in the current call
Share High Res	고해상도 공유	Compartilhar alta resolução	Общий доступ к высокому разрешению	Share the high-resolution version of the current file with others in the current call
Stop Sharing	공유 중지	Parar compartilhamento	Прекратить общий доступ	Stop sharing an image with others in the current call
Start Recording	녹화 시작	Iniciar gravação	Начать запись	Start recording the current video
Stop Recording	녹화 중지	Parar gravação	Остановить запись	Stop recording the current video
Zoom Level 1	확대/축소 레벨 1	Zoom nível 1	Уровень масштабирования 1	Zoom the video to level 1
Zoom Level 2	확대/축소 레벨 2	Zoom nível 2	Уровень масштабирования 2	Zoom the video to level 2
Zoom Level 3	확대/축소 레벨 3	Zoom nível 3	Уровень масштабирования 3	Zoom the video to level 3

Table 5-3 English, Korean, Portuguese (Brazil) and Russian Call Commands (continued)

English	Korean	Portuguese (Brazil)	Russian	ACTION
Telestration Commands				
Telestrate Arrow	화살표 덧그리기	Desenhar seta no Telestration	Телестрация – стрелка	Create a telestration arrow on the current video
Telestrate Circle	원 덧그리기	Desenhar círculo no Telestration	Телестрация – круг	Create a telestration circle on the current video
Telestrate Rectangle	직사각형 덧그리기	Desenhar retângulo no Telestration	Телестрация – прямоугольник	Create a telestration rectangle on the current video
Telestration Colors	덧그리기 색상	Cores do Telestration	Цвета телестрации	Show a popup letting the user select the telestration color
Hide Telestration Colors	덧그리기 색상 표시하지 않음	Ocultar cores do desenho (telestration)	Скрыть цвета телестрации	Hides the colors popup when choosing telestration colors
Erase Telestration	덧그리기 삭제	Apagar o desenho (telestration) (11.4.6) Apagar Desenho	Удалить телестрацию	Erase the current telestration
Undo Telestration	덧그리기 작업 되돌리기	Desfazer o desenho (telestration) (11.4.6) Desfazer Desenho	Отменить телестрацию	Deletes the most recent telestration
Translator Commands				
Translator	번역가	Tradutor	Переводчик	Displays the Translator settings
Hide Translator	번역가 표시하지 않음	Ocultar Tradutor	Скрыть переводчик	Hides the Translator settings
Captions	캡션	Legendas	Субтитры	Toggle to enable or disable captions
Translate from	에서	Traduzir de	Перевод с	Brings drop down menu for Languages
To	(으)로 번역	Para	На	Brings drop down menu for Languages
Additional Settings				
Toggle Mic (Microphone)	토글 마이크	Ativar/desativar o microfone (11.4.6) Comutar Microfone	Вкл./выкл. микрофон	Turns the microphone on or off
Toggle Telephoto	토글 망원	Alternar telefoto	Вкл./выкл. телефото	Turns the telephoto mode on or off (Navigator 500)

Table 5-3 English, Korean, Portuguese (Brazil) and Russian Call Commands (continued)

English	Korean	Portuguese (Brazil)	Russian	ACTION
Mute Microphone	마이크 음소거	Desativar Microfone	Отключить микрофон	Mutes the Mic at the system level
Toggle Torch	토글 토치	Ativar/desativar a lanterna (11.4.6) Comutar Lanterna	Вкл./выкл. фонарик	Turns the camera light on or off

6. File System

English, French, Chinese, and Spanish

Table 6-1 English, French, Chinese, and Spanish File System Commands

English	French	Chinese	Spanish	Action
Files	Fichiers	文件	Archivos	Prefixed by "show" or "hide" to show/hide the files view
Show Files	Afficher Fichiers	显示文件	Mostrar archivos	Shows the list of files
Hide	Masquer	隐藏	Ocultar	Closes the files tab
My Files	Mes Fichiers	我的文件	Mis Archivos	Displays the My Files section of the Files tab
Gallery	Galerie	图库	Galeria	Displays the Gallery section of the Files tab
Upload	Téléchargement	上传	Cargar	Start the upload of a file
Upload Status	Etat des Téléchargements	上传状态	Cargar estado	Display a popup containing the status of any file uploads
Pause	Pause	暂停	Pausado	Pause an upload operation
Resume	Reprendre	恢复	Reanudar	Resume the upload of a file
Cancel	Annuler	取消	Cancelar	Cancel some operation
Cancel All	Tout Annuler	全部取消	Cancelar Todo	Cancel all active uploads
Delete	Supprimer	删除	Borrar	Delete the selected file
Properties	Propriétés	属性	Propiedades	Display the properties for a file
Title	Titre	标题	Titulo	Select the Title field for editing
Description	Description	描述	Descripción	Select the Description field for editing
Keywords	Mots clés	关键字	Palabras claves	Select the Keywords field for editing
Hide Properties	Masquer les Propriétés	隐藏属性	Ocultar propiedades	Hides the properties view
Onsight AI	IA Onsight	Onsight人工智能	AI De Onsight	Opens the Tags Window
Email	Email	电子邮件	Correo Electrónico	Email the selected file to somebody
Share	Partager	共享	Compartir	Share the current file with others in the current call
Stop Sharing	Arrêter le Partage	停止共享	Dejar de Compartir	Stop sharing an image with others in the current call
Play	Jouer	播放	Reproducir	Initiate playback of a recording
Exit Playback	Quitter la lecture	退出回放	Salir de la reproducción	Stop playback of a recording

Table 6-1 English, French, Chinese, and Spanish File System Commands (continued)

English	French	Chinese	Spanish	Action
Cube File Commands				
Cube	Cube	Cube	Cube	Displays the Cube section of the Files tab
Download Files	Télécharger les Fichiers	下载文件	Descargar archivos	Download the selected files
Select All Files	Sélectionnez Tous les Fichiers	选择所有文件	Seleccionar Todos los Archivos	Selects all files in the current list
Deselect All Files	Désélectionner Tous les Fichiers	取消选择所有文件	Anule la selección de todos los archivos	Deselect all selected files
Delete Files	Supprimer des Fichiers	删除文件	Borrar archivos	Delete all selected files
Cancel Download	Annuler le Téléchargement	取消下载	Cancelar Descarga	Cancel all active downloads
Pause Download	Mettre en Pause le Téléchargement	暂停下载	Pausar Descarga	Pause a download operation
Delete Download	Supprimer le Téléchargement	删除下载	Borrar descarga	Delete the selected item
Resume Download	Reprendre le Téléchargement	恢复下载	Reanudar descarga	Resume the download of a file

English, German, Italian, and Japanese

Table 6-2 English, German, Italian, and Japanese File System Commands

English	German	Italian	Japanese	Action
Files	Dateien	File	ファイル	Prefixed by “show” or “hide” to show/hide the files view
Show Files	Anzeigen Dateien	Mostra file	表示するファイル ファイルを表示 (11.4.11)	Shows the list of files
Hide	Ausblenden	Nascondi	隠す	Closes the files tab
Hide Files (Japanese Specific)			ファイルを隠す (11.4.11)	Hide the files view (Japanese Specific)
My Files	Meine Dateien	I miei file	マイファイル	Displays the My Files section of the Files tab
Gallery	Fotogalerie	Galleria	ギャラリー	Displays the Gallery section of the Files tab
Upload	Hochladen	Carica	アップロード	Start the upload of a file
Upload Status	Hochlade-Status	Stato carica	アップロードステータス	Display a popup containing the status of any file uploads
Pause	Anhalten	Sospendi	一時停止	Pause an upload operation
Resume	Fortfahren	Riprendi	再開する アップロード再開 (11.4.11)	Resume the upload of a file
Cancel	Abbrechen	Annulla	キャンセル	Cancel some operation

Table 6-2 English, German, Italian, and Japanese File System Commands (continued)

English	German	Italian	Japanese	Action
Cancel All	Alle abbrechen	Annulla tutto	全てをキャンセル	Cancel all active uploads
Delete	Löschen	Elimina	削除	Delete the selected file
Properties	Eigenschaften	Proprietà	プロパティ	Display the properties for a file
Title	Titel	Titolo	題名 タイトル (11.4.11)	Select the Title field for editing
Description	Beschreibung	Descrizione	説明	Select the Description field for editing
Keywords	Schlüsselwörter	Parole chiave	キーワード	Select the Keywords field for editing
Hide Properties	Ausblenden Eigenschaften	Nascondi Le Proprieta	プロパティを隠す	Hides the properties view
Onsight AI	Onsight künstliche Intelligenz	intelligenza artificiale Onsight	オンサイトAI	Opens the Tags Window
Email	E-Mail	Email	メール	Email the selected file to somebody
Share	Teilen	Condividi	共有 する	Share the current file with others in the current call
Stop Sharing	Freigabe beenden	Arresta condivisione	共有を停止する	Stop sharing an image with others in the current call
Play	Wiedergeben	Riproduci	再生	Initiate playback of a recording
Exit Playback	Wiedergabe beenden	Esci dalla riproduzione	再生を終了する	Stop playback of a recording
Cube File Commands				
Cube	Cube	Cube	Cube	Displays the Cube section of the Files tab
Download Files	Dateien herunterladen	Scarica file	ファイルをダウンロードする	Download the selected files
Select All Files	Alle Dateien auswählen	Seleziona tutti i file	すべてのファイルを選択する	Selects all files in the current list
Deselect All Files	Auswahl aller Dateien aufheben	Deseleziona tutti i file	すべてのファイルの選択を解除する	Deselect all selected files
Delete Files	Dateien löschen	Elimina i file	ファイルを削除する	Delete all selected files
Cancel Download	Herunterladen abbrechen	Annulla download	ダウンロードをキャンセルする	Cancel all active downloads
Pause Download	Herunterladen anhalten	Metti in pausa il download	ダウンロードを一時停止する	Pause a download operation
Delete Download	Download löschen	Elimina download	ダウンロードを削除する	Delete the selected item

Table 6-2 English, German, Italian, and Japanese File System Commands (continued)

English	German	Italian	Japanese	Action
Resume Download	Download Fortsetzen	Riprendi il download	ダウンロードを再開する ダウンロードを続ける (11.4.11)	Resume the download of a file

English, Korean, Portuguese (Brazil) and Russian

Table 6-3 English, Korean, Portuguese (Brazil) and Russian File System Commands

English	Korean	Portuguese (Brazil)	Russian	Action
Files	파일	Arquivos	Файлы	Prefixed by "show" or "hide" to show/hide the files view
Show Files	표시파일	Mostrar arquivos	Показать файлы	Shows the list of files
Hide	표시하지 않음	Ocultar	Скрыть	Closes the files tab
My Files	내 파일	Meus arquivos	Мои файлы	Displays the My Files section of the Files tab
Gallery	갤러리	Galeria	Галерея	Displays the Gallery section of the Files tab
Upload	업로드하기	Carregar	Отправить	Start the upload of a file
Upload Status	업로드 상태	Status do carregamento	Отправки Статус	Display a popup containing the status of any file uploads
Pause	업로드 중지	Pausar	Приостановить	Pause an upload operation
Resume	업로드 재시작	Retomar	Возобновить	Resume the upload of a file
Cancel	취소	Cancelar	Отменить	Cancel some operation
Cancel All	모든 업로드 취소	Cancelar todos	Отменить все	Cancel all active uploads
Delete	삭제	Excluir	Удалить	Delete the selected file
Properties	특성	Propriedades	Свойства	Display the properties for a file
Title	제목	Título	Название	Select the Title field for editing
Description	설명	Descrição	Описание	Select the Description field for editing
Keywords	키워드	Palavras-chave	Ключевые слова	Select the Keywords field for editing
Hide Properties	특성 표시하지 않음	Ocultar propriedades	Скрыть свойства	Hides the properties view
Onsight AI	Onsight 인공지능(AI)	Onsight AI	ИИ Onsight	Opens the Tags Window
Email	이메일	E-mail	Эл. ПОЧТА	Email the selected file to somebody
Share	공유	Compartilhar	Общий доступ	Share the current file with others in the current call
Stop Sharing	공유 중지	Parar compartilhamento	Прекратить общий доступ	Stop sharing an image with others in the current call

Table 6-3 English, Korean, Portuguese (Brazil) and Russian File System Commands (continued)

English	Korean	Portuguese (Brazil)	Russian	Action
Play	재생	Reproduzir	Воспроизвести	Initiate playback of a recording
Exit Playback	재생 종료	Sair da reprodução	Выйти из воспроизведения	Stop playback of a recording
Cube File Commands				
Cube	Cube	Cube	Cube	Displays the Cube section of the Files tab
Download Files	파일 다운로드	Baixar arquivos	Загрузить файлы	Download the selected files
Select All Files	모든 파일 선택	Selecionar todos os arquivos	Выделить все файлы	Selects all files in the current list
Deselect All Files	선택된 모든 파일 선택 해제	Desmarcar todos os arquivos	Отменить выбор всех файлов	Deselect all selected files
Delete Files	파일 삭제	Excluir arquivos	Удалить файлы	Delete all selected files
Cancel Download	다운로드취소	Cancelar download	Отменить загрузку	Cancel all active downloads
Pause Download	다운로드취소	Pausar download	ПАУЗА СКАЧАТЬ	Pause a download operation
Delete Download	다운로드 삭제	Excluir download	УДАЛИТЬ СКАЧАТЬ	Delete the selected item
Resume Download	일시 정지 다운로드	Retomar download	ВОЗОБНОВЛЕНИЕ ЗАГРУЗКИ	Resume the download of a file

7. ViewFinder Commands

English, French, Chinese, and Spanish

Table 7-1 English, French, Chinese, and Spanish ViewFinder Commands

English	French	Chinese	Spanish	Action
Contacts	Contacts	联系人	Contactos	Prefixed by "show" or "hide" to show/hide the contacts list
Files	Fichiers	文件	Archivos	Prefixed by "show" or "hide" to show/hide the files view
System Health	Santé du Système	系统状况	Estado del sistema	Prefixed by "show" or "hide" to show/ hide the system health view
Settings	Réglages	设置	Configuraciones	Prefixed by "show" or "hide" to show/ hide the settings view
Info	Info	信息	Información	Prefixed by "show" or "hide" to show/ hide the program info view
Logout	Déconnexion	等出	Cerrar Sesión	Logs out of the program
Start Recording	Commencer l'Enregistrement	开始录制	Iniciar la Grabación	Start recording the current video
Stop Recording	Arrêter l'Enregistrement	停止录制	Detener la Grabación	Stop recording the current video
Start Streaming	Commencer la Diffusion en Continu	开始流播	Iniciar la transmisión	Start streaming the current video to others in the current call
Stop Streaming	Arrêter la Diffusion en Continu	停止流播	Detener la transmisión	Stop streaming the current video to others in the current call
Take Picture	Prendre une Photo	拍摄照片	Tomar foto	Take a picture from the current video
Zoom Level 1	Niveau de Zoom 1	缩放等级1	Zoom nivel 1	Zoom the video to level 1
Zoom Level 2	Niveau de Zoom 2	缩放等级2	Zoom nivel 2	Zoom the video to level 2
Zoom Level 3	Niveau de Zoom 3	缩放等级3	Zoom nivel 3	Zoom the video to level 3
Translator	Traducteur	翻译器	Traductor	Displays the Translator settings
Telestration Commands				
Telestrate Arrow	Flèche de Téléstrate	远程示范箭头	Dibujar flecha	Create a telestration arrow on the current video
Telestrate Circle	Cercle de Téléstrate	远程示范圆圈	Dibujar círculo	Create a telestration circle on the current video
Telestration Colors	Couleurs de Téléstrate	远程示范色彩	Colores de la telestración	Show a popup letting the user select the telestration color

Table 7-1 English, French, Chinese, and Spanish ViewFinder Commands (continued)

English	French	Chinese	Spanish	Action
Hide Telestration Colors	Masquer les Couleurs de Téléstration	隱藏远程示范色彩	Ocultar los colores de la telestración	Hides the colors popup when choosing telestration colors
Telestrate Rectangle	Rectangle de Téléstrate	远程示范长方形	Dibujar rectángulo	Create a telestration rectangle on the current video
Erase Telestration	Effacer la Téléstration	擦除远程示范	Borrar telestración	Erase the current telestration
Undo Telestration	Annuler la Téléstration	撤销远程示范	Deshacer la Telestración	Deletes the most recent telestration
Additional Settings				
Toggle Mic (Microphone)	Basculer le Microphone	麦克风开关	Alternar el Micrófono	Turns the microphone on or off
Toggle Telephoto	Basculer le Téléobjectif	切换长焦	Alternar teleobjetivo	Turns the telephoto mode on or off (Navigator 500)
Mute Microphone	Couper le microphone	静音麦克风	Silenciar Micrófono	Mutes the Mic at the system level
Toggle Torch	Basculer la Torche	火炬开关	Alternar la Linterna	Turns the camera light on or off

English, German, Italian, and Japanese

Table 7-2 English, German, Italian, and Japanese ViewFinder Commands

English	German	Italian	Japanese	Action
Contacts	Kontakte	Contatti	連絡先	Prefixed by "show" or "hide" to show/hide the contacts list
Show Contacts (Japanese Specific)			連絡先を表示する (11.4.11)	Show the contacts list (Japanese Specific)
Hide Contacts (Japanese Specific)			連絡先を隠す (11.4.11)	Hide the contacts list (Japanese Specific)
Files	Dateien	File	ファイル	Prefixed by "show" or "hide" to show/hide the files view
Show Files (Japanese Specific)			ファイルを表示 (11.4.11)	Show the Files view (Japanese Specific)
Hide Files (Japanese Specific)			ファイルを隠す (11.4.11)	Hide the files view (Japanese Specific)
System Health	Systemzustand	Integrità del sistema	システムの平常性	Prefixed by "show" or "hide" to show/ hide the system health view

Table 7-2 English, German, Italian, and Japanese ViewFinder Commands (continued)

English	German	Italian	Japanese	Action
Show System Health (Japanese Specific)			システムヘルスを表示 (11.4.11)	Show the system health view
Hide System Health (Japanese Specific)			システムヘルスを隠す (11.4.11)	Hide the system health view
Settings	Einstellungen	Impostazioni	設定	Prefixed by "show" or "hide" to show/ hide the settings view
Show Settings (Japanese Specific)			情報の表示(11.4.11)	Show the settings view (Japanese Specific)
Hide Settings (Japanese Specific)			設定を隠す(11.4.11)	Hide the settings view (Japanese Specific)
Info	Info	Informazioni	情報	Prefixed by "show" or "hide" to show/ hide the program info view
Show Info (Japanese Specific)			情報の表示(11.4.11)	Show the program info view
Hide Info (Japanese Specific)			情報を隠す(11.4.11)	Hide the program info view
Logout	Abmelden	Disconnessione	ログアウト	Logs out of the program
Start Recording	Aufnahme starten	Avvia registrazione	録画を開始する	Start recording the current video
Stop Recording	Aufnahme beenden	Arresta registrazione	録画を止停 する	Stop recording the current video
Start Streaming	Streaming starten	Avvia streaming	ストリーミングを開始する	Start streaming the current video to others in the current call
Stop Streaming	Streaming beenden	Arresta streaming	ストリーミングを停止する	Stop streaming the current video to others in the current call
Take Picture	Foto aufnehmen	Scatta foto	写真を撮る	Take a picture from the current video
Zoom Level 1	Zoomen auf Stufe 1	Ingrandisci al livello 1	ズームレベル1	Zoom the video to level 1
Zoom Level 2	Zoomen auf Stufe 2	Ingrandisci al livello 2	ズームレベル2	Zoom the video to level 2
Zoom Level 3	Zoomen auf Stufe 3	Ingrandisci al livello 3	ズームレベル3	Zoom the video to level 3
Translator	ubersetzer	Traduttore	翻訳者 翻訳機能 (11.4.11)	Displays the Translator settings

Table 7-2 English, German, Italian, and Japanese ViewFinder Commands (continued)

English	German	Italian	Japanese	Action
Telestration Commands				
Telestrate Arrow	Pfeil für Videomarkierung	Disegna freccia	矢印をテレストレートする アノテーション、矢印 (11.4.11)	Create a telestration arrow on the current video
Telestrate Circle	Kreis für Videomarkierung	Disegna cerchio	円形をテレストレートする アノテーション、遠景 (11.4.11)	Create a telestration circle on the current video
Telestration Colors	Farben für Videomarkierung	Colori note sullo schermo	テレストレーションカラー アノテーション色 (11.4.11)	Show a popup letting the user select the telestration color
Hide Telestration Colors	Videomarkierungs-Farben ausblenden	Nascondi colori delle note sullo schermo	テレストレーションカラーを隠す アノテーション色を隠す (11.4.11)	Hides the colors popup when choosing telestration colors
Telestrate Rectangle	Rechteck für Videomarkierung	Disegna rettangolo	テレストレート長方形 アノテーション、四角 (11.4.11)	Create a telestration rectangle on the current video
Erase Telestration	Videomarkierung löschen	Cancella note sullo schermo	テレストレーションを消去する アノテーションを削除 (11.4.11)	Erase the current telestration
Undo Telestration	Videomarkierung rückgängig machen	Annulla note sullo schermo	テレストレーションを元に戻す アノテーションを元に戻す (11.4.11)	Deletes the most recent telestration
Additional Settings				
Toggle Mic (Microphone)	Mikrofon umschalten	Attiva/disattiva microfono	マイクを切り替える	Turns the microphone on or off
Toggle Telephoto	Tele umschalten	Abilita/disabilita il teleobiettivo	望遠に切り替える	Turns the telephoto mode on or off (Navigator 500)
Mute Microphone	Mikrofon aus	Disabilita Microfono	マイクを無効にする	Mutes the Mic at the system level
Toggle Torch	Lampe umschalten	Attiva/disattiva torcia	トグルトーチ トグルライト (11.4.11)	Turns the camera light on or off

English, Korean, Portuguese (Brazil) and Russian

Table 7-3 English, Korean, Portuguese (Brazil) and Russian ViewFinder Commands

English	Korean	Portuguese (Brazil)	Russian	Action
Contacts	연락처	Contatos	Контакты	Prefixed by "show" or "hide" to show/hide the contacts list
Files	파일	Arquivos	Файлы	Prefixed by "show" or "hide" to show/hide the files view
System Health	시스템 상태	Saúde do sistema	Работоспособность системы	Prefixed by "show" or "hide" to show/ hide the system health view
Settings	설정	Configurações	Настройки	Prefixed by "show" or "hide" to show/ hide the settings view
Info	정보	Informações	Сведения	Prefixed by "show" or "hide" to show/ hide the program info view
Logout	로그아웃	Logoff (Not supported in 11.4.6)	Выход	Logs out of the program
Start Recording	녹화 시작	Iniciar gravação	Начать запись	Start recording the current video
Stop Recording	녹화 중지	Parar gravação	Остановить запись	Stop recording the current video
Start Streaming	스트리밍 시작	Iniciar transmissão	Начать потоковую передачу	Start streaming the current video to others in the current call
Stop Streaming	스트리밍 중지	Parar compartilhamento	Остановить потоковую передачу	Stop streaming the current video to others in the current call
Take Picture	사진 찍기	Tirar foto	Сделать снимок	Take a picture from the current video
Zoom Level 1	확대/축소 레벨 1	Zoom nível 1	Уровень масштабирования 1	Zoom the video to level 1
Zoom Level 2	확대/축소 레벨 2	Zoom nível 2	Уровень масштабирования 2	Zoom the video to level 2
Zoom Level 3	확대/축소 레벨 3	Zoom nível 3	Уровень масштабирования 3	Zoom the video to level 3
Translator	번역가	Tradutor	Переводчик	Displays the Translator settings
Telestration Commands				
Telestrate Arrow	화살표 덧그리기	Desenhar seta no Telestration	Телестрация – стрелка	Create a telestration arrow on the current video
Telestrate Circle	원 덧그리기	Desenhar círculo no Telestration	Телестрация – круг	Create a telestration circle on the current video
Telestration Colors	덧그리기 색상	Cores do Telestration	Цвета телестрации	Show a popup letting the user select the telestration color

Table 7-3 English, Korean, Portuguese (Brazil) and Russian ViewFinder Commands (continued)

English	Korean	Portuguese (Brazil)	Russian	Action
Hide Telestration Colors	덧그리기 색상 표시하지 않음	Ocultar cores do desenho (telestration)	Скрыть цвета телестрации	Hides the colors popup when choosing telestration colors
Telestrate Rectangle	직사각형 덧그리기	Desenhar retângulo no Telestration	Телестрация – прямоугольник	Create a telestration rectangle on the current video
Erase Telestration	덧그리기 삭제	Apagar o desenho (telestration) (11.4.6) Apagar Desenho	Удалить телестрацию	Erase the current telestration
Undo Telestration	덧그리기 작업 되돌리기	Desfazer o desenho (telestration) (11.4.6) Desfazer Desenho	Отменить телестрацию	Deletes the most recent telestration
Additional Settings				
Toggle Mic (Microphone)	토글 마이크	Ativar/desativar o microfone (11.4.6) Comutar Microfone	Вкл./выкл. микрофон	Turns the microphone on or off
Toggle Telephoto	토글 망원		Alternar telefoto	Turns the telephoto mode on or off (Navigator 500)
Mute Microphone	마이크 음소거	Desativar Microfone	Отключить микрофон	Mutes the Mic at the system level
Toggle Torch	토글 토치	Ativar/desativar a lanterna (11.4.6) Comutar Lanterna	Вкл./выкл. фонарик	Turns the camera light on or off

8. Show Information Commands

English, French, Chinese, and Spanish

Table 8-1 English, French, Chinese, and Spanish Show Information Commands

English	French	Chinese	Spanish	ACTION
Info	Info	信息	Información	Prefixed by “show” or “hide” to show/hide the program info view
Show Info	Afficher Info	显示信息	Mostrar Información	Shows the help information view
Hide Info	Masquer Info	隐藏信息	Ocultar Información	Hides the help information view
User Manual	Manuel de l'Utilisateur	用户手册	Manual del usuario	Shows the User Manual information
Support	Support	客户支持	Soporte técnico	Shows the Support information
Email Logs	Envoyer Les Logs Par Email	电子邮件日志	Registros de correo electrónico	Connects to an email app to send the logs
Export Logs	Exporter les Logs	导出日志	Exportar los registros	Saves the logs to the logs folder in HMT storage
About	A Propos	关于	Acerca de	Shows the About page

English, German, Italian, and Japanese

Table 8-2 English, German, Italian, and Japanese Show Information Commands

English	German	Italian	Japanese	ACTION
Info	info	Informazioni	情報	Prefixed by “show” or “hide” to show/hide the program info view
Show Info	Info anzeigen	Mostra informazioni	表示する情報 情報を表示する (11.4.11)	Shows the help information view
Hide Info	Info Ausblenden	Nascondi Informazioni	隠す情報 情報を隠す (11.4.11)	Hides the help information view
User Manual	Benutzerhandbuch	Manuale d'uso	ユーザーマニュアル	Shows the User Manual information
Support	Support	Assistenza	サポート サポート情報 (11.4.11)	Shows the Support information
Email Logs	E-Mail-Protokoll	Registri email	メールログ	Connects to an email app to send the logs
Export Logs	Protokolle exportieren	Esporta registri	ログをエクスポートする ログ送信 (11.4.11)	Saves the logs to the logs folder in HMT storage
About	Info	nformazioni	概要	Shows the About page

English, Korean, Portuguese (Brazil) and Russian

Table 8-3 English, Korean, Portuguese (Brazil) and Russian Show Information Commands

English	Korean	Portuguese (Brazil)	Russian	Action
Info	정보	Informações	Сведения	Prefixed by “show” or “hide” to show/hide the program info view
Show Info	정보 표시	Mostrar informações	Показать сведения	Shows the help information view
Hide Info	정보 숨기기	Ocultar informações	Скрыть Сведения	Hides the help information view
User Manual	사용자 안내서	Manual do usuário	Руководство пользователя	Shows the User Manual information
Support	지원	Suporte	Поддержка	Shows the Support information
Email Logs	이메일 로그	Logs de e-mails	Журналы эл. почты	Connects to an email app to send the logs
Export Logs	로그 내보내기	Exportar logs	Экспортировать журналы	Saves the logs to the logs folder in HMT storage
About	관련	Sobre	О продукте	Shows the About page

9. Cube Commands

English, French, Chinese, and Spanish

Table 9-1 English, French, Chinese, and Spanish Cube Commands

English	French	Chinese	Spanish	Action
Bluetooth Commands				
Settings	Réglages	设置	Configuraciones	Prefixed by "show" or "hide" to show/ hide the settings view
Cube	Cube	Cube	Cube	Brings up the Cube Settings
Enable Bluetooth	Activer Bluetooth	启用蓝牙	Habilitar Bluetooth	Enables the HMT Bluetooth
WiFi - Direct Commands				
Accept	Accepter	接受	Aceptar	Accepts the Invitation to Connect from Cube
Decline	Refuser	拒绝	Rechazar	Declines the Invitation to Connect from Cube
Infrastructure Mode Commands				
Configure Wi-Fi	Configuration Wifi	配置Wi-Fi	Configurar Wi-Fi	Configure the Wi-Fi for Cube communications
Network Name	Nom du Reseau	网络名	Nombre de la red	Selects the Network name field for editing
Security	Securite	安全	Seguridad	Selects the Security field for editing
Password	Mot de Passe	密码	Contraseña	Select the password field for editing
Join	Joindre	加入	Unirse	Joins the selected network
Choose another network...	Choisir un autre réseau...	选择其他网络...	Seleccione otra red...	Choose a different network for Cube communications
Add	Ajouter	添加	Añadir	Add the manually configured network
Refresh	Rafraîchir	刷新	Refrescar	Refresh the list of Wi-Fi networks for the Cube
Cube Troubleshooting				
Check for Updates	researcher des Mises a Jour	查验更新,	Verifique si hay actualizaciones	Checks for an update for the Cube firmware
Forget Cube	Oublier ce Cube	忘记Cube	Olvidar Cube	Forgets the pairing with a Cube
Reset Network	Réinitialiser le Réseau	重置网络	Restablecer la red	Clears all network settings
Factory Reset	Réinitialisation aux paramètres d'usine	出厂重置	Restablecimiento de fábrica	Clears the Cube of all configuration and data files
Switching Video Sources with Cube Connected				
Show Video Sources	Afficher les Sources Vidéo	显示视频源	Mostrar Fuentes de Video	Shows a popup with the available video sources

Table 9-1 English, French, Chinese, and Spanish Cube Commands (continued)

English	French	Chinese	Spanish	Action
Hide Video Sources	Masquer les Sources Vidéo	隐藏视频源	Ocultar fuentes de Video	Hides the popup showing the video sources
Source RealWear	Selectionner RealWear Comme Source	源RealWear	Vista usando RealWear	Select the RealWear glasses as the current video source
Source Cube	Selectionner Cube Comme Source	源Cube	Vista normal Cube	Select the Cube's normal view as the current video source
Source Thermal	Selectionner La Vision Thermique Comme Source	源Thermal	Vista en modo térmico	Select the Cube's thermal view as the current video source
Source Fusion	Selectionner Fusion Comme Source	源Fusion	Vista en modo fusión	Select the Cube's fusion view as the current video source
Cube Functions				
Show Cube Functions	Afficher les Fonctions Cube	显示Cube功能	Mostrar las funciones de Cube	Shows a popup containing Cube commands
Hide Cube Functions	Masquer les Fonctions de Cube	隐藏Cube功能	Ocultar las funciones de Cube	Hides a popup containing Cube commands
Toggle Laser	Basculer le Laser	激光开关	Alternar el Láser	Turns the laser on or off
Toggle Spot Temperature	Basculer la Température d'Endroit	测点温度开关	Cambiar la temperatura en el punto	Turns the view of the spot temperature on or off
Toggle Temperature Unit	Basculer l'Appareil de Température	温度单位转换	Cambiar la unidad de temperatura	Switches between Fahrenheit and Celsius
Place Mode	Mode Place	放置模式	Modo de cuadrícula	Enter place mode
Gloss	Brillant	亮光	Brillo	Select the gloss view
Matte	Mat	磨砂	Mate	Select the matte view
Semi Gloss	Semi-Brillant	半亮光	Semibrillante	Select the semigloss view
Semi Matte	Semi-Mat	半哑光	Semimate	Select the semimatte view
Skin	Habillage	皮肤	aspecto visual	Select the Skin View
Fusion Mode and Alignment Adjustment				
Slider Mode	Mode Curseur	滑块模式	Barra de desplazamiento	Enter slide mode
0-255	0-255	0-255	0-255	Manually set the current slider numeric value (i.e., 17)
Exit Manual Mode	Quitter le Mode Manuel	退出手动模式	Salir del modo manual	Exit from manual mode

English, German, Italian, and Japanese

Table 9-2 English, German, Italian, and Japanese Cube Commands

English	German	Italian	Japanese	Action
Bluetooth Commands				
Settings	Einstellungen	Impostazioni	設定	Prefixed by "show" or "hide" to show/ hide the settings view
Show Settings (Japanese Specific)			設定を表示 (11.4.11)	Show the settings view (Japanese Specific)
Hide Settings (Japanese Specific)			設定を隠す (11.4.11)	Hide the settings view (Japanese Specific)
Cube	Cube	Cube	Cube	Brings up the Cube Settings
Enable Bluetooth	Bluetooth aktivieren	Abilita Bluetooth	Bluetoothを有効にする	Enables the HMT Bluetooth
WiFi - Direct Commands				
Accept	Annehmen	Accetta	許可	Accepts the Invitation to Connect from Cube
Decline	Ablehnen	Rifiuta	減少	Declines the Invitation to Connect from Cube
Infrastructure Mode Commands				
Configure Wi-Fi	Wi-Fi konfigurieren	Configura Wi-Fi	Wi-Fiを構成する	Configure the Wi-Fi for Cube communications
Network Name	Netzwerkname	Nome della rete	ネットワーク名	Selects the Network name field for editing
Security	Sicherheit	Sicurezza	セキュリテイ	Selects the Security field for editing
Password	Passwort	Password	パスワード	Select the password field for editing
Join	Verbinden	Unisciti	参加する	Joins the selected network
Choose another network...	Ein anderes Netzwerk wählen...	Scegli un'altra rete...	他のネットワークを選択する...	Choose a different network for Cube communications
Add	Hinzufügen	Aggiungi	追加	Add the manually configured network
Refresh	Aktualisieren	Ricaricare	リフレッシュ	Refresh the list of Wi-Fi networks for the Cube
Cube Troubleshooting				
Check for Updates	Aktualisierungen suchen	Controlla la disponibilita di aggiornmenti	アップデート版が確認する	Check an update for the Cube firmware
Forget Cube	Cube vergessen	Dimentica Cube	Cubeの自動接続をオフにする	Forgets the pairing with a Cube
Reset Network	Netzwerk zurücksetzen	Reimposta rete	ネットワークをリセットする	Clears all network settings

Table 9-2 English, German, Italian, and Japanese Cube Commands (continued)

English	German	Italian	Japanese	Action
Factory Reset	Zurück auf Werkseinstellungen	Rispristino impostazioni di fabbrica	ファクトリーリセット	Clears the Cube of all configuration and data files
Switching Video Sources with Cube Connected				
Show Video Sources	Videoquellen anzeigen	Mostra sorgenti video	ビデオソースを表示	Shows a popup with the available video sources
Hide Video Sources	Videoquellen ausblenden	Nascondi le sorgenti video	ビデオソースを隠す	Hides the popup showing the video sources
Source RealWear	RealWear - Quelle Auswählen	Sorgente RealWear	ソース REALWEAR	Select the RealWear glasses as the current video source
Source Cube	Cube - Quelle Auswählen	Sorgente Cube	ソース CUBE	Select the Cube's normal view as the current video source
Source Thermal	Thermal Quelle Auswählen	Sorgente Termica	ソースサーマル	Select the Cube's thermal view as the current video source
Source Fusion	Fusion Quelle Auswählen	Sorgente Fusion	ソースフュージョン	Select the Cube's fusion view as the current video source
Cube Functions				
Show Cube Functions	Cube-Funktionen anzeigen	Mostra le funzioni di Cube	Cube機能の表示する	Shows a popup containing Cube commands
Hide Cube Functions	Cube-Funktionen ausblenden	Nascondi le funzioni di Cube	Cube 機能を隠す	Hides a popup containing Cube commands
Toggle Laser	Laser umschalten	Attiva/disattiva laser	トグルレーザーを切り替える	Turns the laser on or off
Toggle Spot Temperature	Punkttemperatur umschalten	Attiva/disattiva temperatura spot	スポット温度を切り替える	Turns the view of the spot temperature on or off
Toggle Temperature Unit	Temperatureinheit umschalten	Seleziona unità temperatura	温度単位を切り替える	Switches between Fahrenheit and Celsius
Place Mode	Positionsmodus	Modalità Luogo	プレースモード	Enter place mode
Gloss	Glänzend	Lucido	光沢	Select the gloss view
Matte	Matt	Opaco	マット	Select the matte view
Semi Gloss	Seidenmatt	Semi-lucido	半光沢	Select the semigloss view
Semi Matte	Halbmatt	Semi-opaco	セミマット	Select the semimatte view
Skin	Skin	Skin	スキン	Select the Skin View
Fusion Mode and Alignment Adjustment				
Slider Mode	Slider Modus	Modalità cursore	スライダーモード	Enter slide mode
0-255	0-255	0-255	0-255	Prefix when showing the current slider numeric value (i.e., Value: 17)
Exit Manual Mode	Manuellen Modus beenden	Esci dalla modalità manuale	手動モードを終了	Exit from manual mode

English, Korean, Portuguese (Brazil) and Russian

Table 9-3 English, Korean, Portuguese (Brazil) and Russian Cube Commands

English	Korean	Portuguese (Brazil)	Russian	Action
Bluetooth Commands				
Settings	설정	Configurações	Настройки	Prefixed by "show" or "hide" to show/ hide the settings view
Cube	Cube	Cube	Cube	Brings up the Cube Settings
Enable Bluetooth	블루투스 활성화	Habilitar o Bluetooth	Включить Bluetooth	Enables the HMT Bluetooth
WiFi - Direct Commands				
Accept	수락	Aceitar	Принять	Accepts the Invitation to Connect from Cube
Decline	거부	Recusar	Отклонить	Declines the Invitation to Connect from Cube
Infrastructure Mode Commands				
Configure Wi-Fi	와이파이 구성	Configurar Wi-Fi	Настроить Wi-Fi	Configure the Wi-Fi for Cube communications
Network Name	네트워크 이름	Nome da rede	Имя сети	Selects the Network name field for editing
Security	보안	Segurança	Безопасность	Selects the Security field for editing
Password	비밀번호	Senha	Пароль	Select the password field for editing
Join	연결	Ingressar	Подключиться	Joins the selected network
Choose another network...	다른 네트워크를 선택하십시오...	Escolher outra rede...	Выбрать другую сеть...	Choose a different network for Cube communications
Add	추가	Adicionar	Добавить	Add the manually configured network
Refresh	새로고침	Atualizar	ОБНОВЛЕНИЕ	Refresh the list of Wi-Fi networks for the Cube
Cube Troubleshooting				
Check for Updates	업데이트 확인	Verificar Atualizacoes	Проверить наличие обновлений	Check for an update of the Cube firmware
Forget Cube	Cube 삭제	Esquecer o Cube	Забывать Cube	Forgets the pairing with a Cube
Reset Network	네트워크 재설정	Redefinir rede	Сбросить сеть	Clears all network settings
Factory Reset	출고 시 모드로 초기화	Redefinição de fábrica	Сброс на заводские настройки	Clears the Cube of all configuration and data files
Switching Video Sources with Cube Connected				
Show Video Sources	동영상 소스 표시	Mostrar fontes de vídeo	Показать источники видео	Shows a popup with the available video sources
Hide Video Sources	동영상 소스 표시하지 않음	Ocultar fontes de vídeo	Скрыть источники видео	Hides the popup showing the video sources

Table 9-3 English, Korean, Portuguese (Brazil) and Russian Cube Commands (continued)

English	Korean	Portuguese (Brazil)	Russian	Action
Source RealWear	리얼웨어	RealWear de origem	Исходное устройство RealWear	Select the RealWear glasses as the current video source
Source Cube	소스 Cube	Cube de origem	Исходное устройство Cube	Select the Cube's normal view as the current video source
Source Thermal	소스	Térmico de origem	Исходное устройство Thermal	Select the Cube's thermal view as the current video source
Source Fusion	퓨전	Fusão de origem	Исходное устройство Fusion	Select the Cube's fusion view as the current video source
Cube Functions				
Show Cube Functions	Cube 기능 표시	Mostrar funções do Cube	Показать функции Cube	Shows a popup containing Cube commands
Hide Cube Functions	Cube 기능 표시하지 않음	Ocultar funções do Cube	Скрыть функции Cube	Hides a popup containing Cube commands
Toggle Laser	토글 레이저	Ativar/desativar o laser (Not supported in 11.4.6)	Вкл./вык. лазер	Turns the laser on or off
Toggle Spot Temperature	토글 위치의 온도	Ativar/desativar a temperatura pontual (11.4.6) Comutar temperatura pontual	Вкл./вык. измерение температуры в точке	Turns the view of the spot temperature on or off
Toggle Temperature Unit	토글 온도의 단위	Ativar/desativar a unidade de temperatura (11.4.6) Comutar unidade de temperatura	Переключение единиц измерения температуры	Switches between Fahrenheit and Celsius
Place Mode	좌표 모드	Modo Local	Режим размещения	Enter place mode
Gloss	광택	Brilho	Глянцевый	Select the gloss view
Matte	무광택	Fosco	Матовый	Select the matte view
Semi Gloss	반 광택	Semibrilhante	Полуглянцевый	Select the semigloss view
Semi Matte	반 무광택	Semifosco	Полуматовый	Select the semimatte view
Skin	스킨	Capa	Оформление	Select the Skin View
Fusion Mode and Alignment Adjustment				
Slider Mode	슬라이더 모드	Modo deslizante	РЕЖИМ СЛАЙДЕРА	Enter slide mode
0-255	0-255	0-255	0-255	Manually set the current slider numeric value (i.e., 17)
Exit Manual Mode	수동 모드 종료	Sair do modo Manual	Выйти из ручного режима	Exit from manual mode

Index

- A**
 - About 39
 - Accept 19, 41
 - Active Call Commands 19
 - Add 41
 - Additional Settings 19, 33
 - AI 27
 - Application Management 5
- B**
 - Bluetooth Commands 41
 - Browser Back 9
 - Bypass proxy server for local addresses 9
- C**
 - Call [Name] 17, 19
 - Cancel 9, 19, 27
 - Cancel All 27
 - Cancel Download 27
 - Captions 19
 - Capture Mode 9
 - Choose another network... 41
 - Close 9
 - Configure Wi-Fi 41
 - Contacts 17, 33
 - Cube 27, 41
 - Cube File Commands 27
 - Cube Functions 41
- D**
 - Decline 19, 41
 - Delete 27
 - Delete Download 27
 - Delete Files 27
 - Description 27
 - Deselect All 27
 - Details 15
 - Disconnect Call 19
 - Dismiss All 5, 5
 - Domain 9
 - Download Files 27
- E**
 - Email 27
 - Email Logs 39
 - Enable Bluetooth 41
 - Enable Single Sign On 9
 - Enabling Single Sign On 9
 - Erase Telestration 19, 33
 - Exit 27
 - Exit Manual Mode 41
 - Export Logs 39
- F**
 - Factory Reset 41
 - Files 27, 27, 27, 33
 - Forget Cube 41
 - Forgot Password 9
- G**
 - Gallery 27
 - Gloss 41
- H**
 - Hide 5, 15, 27
 - Hide Cube Functions 41
 - Hide Help 5
 - Hide Info 39
 - Hide My Files 27
 - Hide Telestration Colors 19, 33
 - Hide Tool Tips 5
 - Hide Translator 19
 - Hide Video Sources 41
- I**
 - Info 33, 39
 - Infrastructure Mode Commands 41
- J**
 - Join 41
- K**
 - Keywords 27
- L**
 - Login 9, 9
 - Logout 5, 9, 33
- M**
 - Making a Call 19
 - Matte 41
 - Mute Microphone 19, 33
- N**
 - Navigate Back 5
 - Navigate Home 5
 - Network Name 41
- O**
 - Onsight 27
- P**
 - Password 9, 9, 41
 - Pause 27
 - Pause Download 27
 - Place Mode 41
 - Play 27
 - Playback 27
 - Port 9
 - Preferred User Agent 9
 - Properties 27, 27
 - Proxy 9
 - Proxy TypeAddress 9
- R**
 - Receiving a Call 19
 - Recent Applications 5
 - Refresh Cube 41
 - Register 9
 - Remember Me 9
 - Reset Network 41
 - Reset Password 9
 - Restart Download 27
 - Resume 27
 - Resume Download 27
- S**
 - Scan Code 9
 - Scroll Down 5, 17
 - Scroll Up 5, 17
 - Search Contacts 17
 - Security 41
 - Select All 27
 - Select item # 5, 17
 - Semi Gloss 41
 - Semi Matte 41
 - Setting up a Proxy Server 9
 - Settings 9, 33, 41

- Share 27
- Share High Res 19
- Share Picture 19
- Show 5
- Show Cube Functions 41
- Show Files 27
- Show Help 5
- Show Info 39
- Show Password 9
- Show System Health 15
- Show Tool Tips 5
- Show Video Sources 41
- Skin Fusion Mode and Alignment Adjustment 41
- Slider Mode 41
- Source Cube 41
- Source Fusion 41
- Source RealWear 41
- Source Thermal 41
- Standard Login Method 9
- Start Recording 19, 33
- Start Streaming 19, 33
- Stop Recording 19, 33
- Stop Sharing 19, 27
- Stop Streaming 19, 33
- Switching Video Sources with Cube Connected 41
- System Health 15, 33

T

- Take Picture 19, 33
- Telestrate Arrow 19, 33
- Telestrate Circle 19, 33
- Telestrate Rectangle 19, 33
- Telestration Colors 19, 33
- Telestration Commands 19, 33
- Title 27
- To 19
- Toggle Laser 41
- Toggle Mic (Microphone) 19, 33
- Toggle Spot Temperature 41
- Toggle Telephoto 19, 33
- Toggle Temperature Unit 41
- Toggle Torch 19, 33
- Translate from 19
- Translator 19, 33
- Translator Commands 19
- Troubleshooting 41

U

- Undo Telestration 19, 33
- Update 41
- Upload 27
- Upload Status 27
- User Manual Support 39
- User Name 9
- Username 9

V

- Value 41

W

- WiFi - Direct Commands 41

Z

- Zoom Level 1 19, 33
- Zoom Level 2 19, 33
- Zoom Level 3 19, 33